

Install Ioncube Loader

The example is for PHP 5.6 as provided by Ondřej Surý repository. The procedure is identical for any PHP version that is provided by Ondřej Surý repository. You MUST just adapt the path for the PHP extension which you can retrieve easily by running the command shown below.

ROOT

```
# cd /usr/local/src/ # wget
https://downloads.ioncube.com/loader\_downloads/ioncube\_loaders\_lin\_x86-64.tar.gz # tar xzf
ioncube_loaders_lin_x86-64.tar.gz # cd ioncube/ # cp ioncube_loader_lin_5.6.so
/usr/lib/php/20131226/ioncube.so
```

The following command make you able to find the correct path for PHP extensions:

USER

```
# php5.6 -i | grep extension_dir
```

Creation of the INI file for the PHP 5.6 Ioncube Loader extension

Create the `/etc/php/5.6/mods-available/ioncube.ini` file with the following content

```
; configuration for php ionCube PHP Loader module
; priority=01
zend_extension=ioncube.so
```

Activation

ROOT

```
# phpenmod ioncube
```

Activation check

```
php5.6 -v
PHP 5.6.36-1+0~20180505045733.13+jessie~1.gbp9b5cab (cli)
Copyright (c) 1997-2016 The PHP Group
Zend Engine v2.6.0, Copyright (c) 1998-2016 Zend Technologies
    with the ionCube PHP Loader (enabled) + Intrusion Protection from
ioncube24.com (unconfigured) v10.2.1, Copyright (c) 2002-2018, by ionCube
Ltd.
    with Zend OPcache v7.0.6-dev, Copyright (c) 1999-2016, by Zend
Technologies
```

Service restart

If you use PHP-FPM

ROOT

```
# service php5.6-fpm restart
```

If you use FCGID:

ROOT

```
# service apache2 restart
```

From:

<https://wiki.i-mscp.net/> - **i-MSCP Documentation**

Permanent link:

<https://wiki.i-mscp.net/doku.php?id=3rdparty:ioncube&rev=1526925878>



Last update: **2018/05/21 19:04**