

# Install Ioncube Loader

The example is for PHP 5.6 as provided by Ondřej Surý repository. The procedure is identical for any PHP version that is provided by Ondřej Surý repository. You **MUST** just adapt the path for the PHP extensions.

First, let's retrieve the path for PHP extensions:

USER

```
# php5.6 -i | grep extension_dir extension_dir ⇒ /usr/lib/php/20131226 ⇒ /usr/lib/php/20131226
```

So here, the path is:

```
/usr/lib/php/20131226
```

Download, extract and install the IonCube Loader for the PHP 5.6 version:

ROOT

```
# cd /usr/local/src/ # wget
https://downloads.ioncube.com/loader\_downloads/ioncube\_loaders\_lin\_x86-64.tar.gz # tar xzf
ioncube_loaders_lin_x86-64.tar.gz # cd ioncube/ # cp ioncube_loader_lin_5.6.so
/usr/lib/php/20131226/ioncube.so
```

Create the /etc/php/5.6/mods-available/ioncube.ini file with the following content:

```
; configuration for php ionCube PHP Loader module
; priority=01
zend_extension=ioncube.so
```

Activate the IonCube Loader for PHP 5.6

ROOT

```
# phpenmod ioncube
```

Check that the IonCube Loader for PHP 5.6 has been correctly activated:

```
php5.6 -v
PHP 5.6.36-1+0~20180505045733.13+jessie~1.gbp9b5cab (cli)
Copyright (c) 1997-2016 The PHP Group
Zend Engine v2.6.0, Copyright (c) 1998-2016 Zend Technologies
    with the ionCube PHP Loader (enabled) + Intrusion Protection from
ioncube24.com (unconfigured) v10.2.1, Copyright (c) 2002-2018, by ionCube
Ltd.
    with Zend OPcache v7.0.6-dev, Copyright (c) 1999-2016, by Zend
Technologies
```

Restart the service:

If you use PHP-FPM

ROOT

```
# service php5.6-fpm restart
```

If you use FCGID:

ROOT

```
# service apache2 restart
```

From:

<https://wiki.i-mscp.net/> - **i-MSCP Documentation**

Permanent link:

<https://wiki.i-mscp.net/doku.php?id=3rdparty:ioncube&rev=1526926166>



Last update: **2018/05/21 19:09**