

Plugin Management Interface

Access to the plugins management interface

Only administrators can access the plugin management interface which is located in the settings section.

PLUGIN INSTALLATION

To install a plugin, you must in order:

1. login as admin and go to the plugin management interface
2. upload the plugin archive
3. click on the Update Plugin button
4. cClick on the installation icone

PLUGIN ACTIVATION

To activate a plugin, you must in order:

1. login as admin and go to the plugin management interface
2. click on the deactivation icone

PLUGIN UPDATE

To update a plugin, you must in order:

login as admin and go to the plugin management interface upload the plugin archive click on the **Update Plugin** button

PLUGIN PROTECTION

In some cases, it can be interesting to protect a specific plugin against deactivation. For instance, the first administrator, which has full access to the server, can create other administrator accounts which have the same permissions on the panel but not an SSH access.

To protect a plugin, you must in order:

1. login as admin and go to the plugn management interface
2. click on the protect icone

Note: When clicking on the protect icone, the plugin manager creates or updates a

protected_plugins.php file into the **gui/data/persistent** directory. This file contains a list of all protected plugins. If a plugin is listed in this file, the **deactivate** icon is no longer available for it in the plugin management interface.

PLUGIN DEACTIVATION

First, if the plugin you want to deactivate is protected, you must start by editing the **gui/data/persistent/protected_plugins.php** file to remove it from the protected plugin list. If the plugin for which you want remove the protection is the only one listed, you can simply remove the file.

To deactivate a plugin, you must in order:

1. unprotect the plugin by removing it from the **gui/data/persistent/protected_plugins.php** (only needed if the plugin is protected)
2. login as admin and go to the plugin management interface
3. click on the deactivation icon

PLUGIN UNINSTALLATION

To uninstall a plugin, you must in order

1. login as admin and go to the plugin management interface
2. click on the uninstallation icon

PLUGIN DELETION

To delete a plugin you must in order:

1. login as admin and go to the plugin management interface
2. deactivate and/or uninstall the plugin
3. click on the deletion icon

Changing plugin configuration

To change the configuration for a specific plugin, you must in order:

1. edit the plugin configuration file
2. login as admin and go to the plugin management interface
3. click on the **Update Plugins** button

See [Plugin Configuration](#) for further details.

From:

<https://wiki.i-mscp.net/> - **i-MSCP Documentation**

Permanent link:

<https://wiki.i-mscp.net/doku.php?id=plugins:management&rev=1393217021>



Last update: **2014/02/24 04:43**