# **Plugin Management Interface**

# Access to the plugins management interface

Only administrators can access the plugin management interface which is located in the settings section.

#### **PLUGIN INSTALLATION**

To install a plugin, you must in order:

- 1. login as admin and go to the plugin management interface
- 2. upload the plugin archive
- 3. click on the Update Plugin button
- 4. cLick on the installation icone

## **PLUGIN ACTIVATION**

To activate a plugin, you must in order:

- 1. login as admin and go to the plugin management interface
- 2. click on the deactivation icone

#### **PLUGIN UPDATE**

To update a plugin, you must in order:

login as admin and go to the plugin management interface upload the plugin archive click on the **Update Plugin** button

#### PLUGIN PROTECTION

In some cases, it can be interesting to protect a specific plugin <u>against deactivation</u>. For instance, the first administrator, which has full access to the server, can create other administrator accounts which have the same permissions on the panel but not an SSH access.

To protect a plugin, you must in order:

- 1. login as admin and go to the plugn management interface
- 2. click on the protect icone

**Note:** When clicking on the protect icone, the plugin manager creates or updates a

**protected\_plugins.php** file into the **gui/data/persistent** directory. This file contains a list of all protected plugins. If a plugin is listed in this file, the **deactivate** icone is no longer available for it in the plugin management interface.

### **PLUGIN DEACTIVATION**

To deactivate a plugin, you must in order:

- unprotect the plugin by removing it from the gui/data/persistent/protected\_plugins.php (only needed if the plugin is protected)
- 2. login as admin and go to the plugin management interface
- 3. click on the deactivation icone

## **PLUGIN UNINSTALLATION**

To uninstall a plugin, you must in order

- 1. login as admin and go to the plugin management interface
- 2. click on the uninstallation icone

#### **PLUGIN DELETION**

To delete a plugin you must in order:

- 1. login as admin and go to the plugin mangement interface
- 2. deactivate and/or uninstall the plugin
- 3. click on the deletion icone

# Changing plugin configuration

To change the configuration for a specific plugin, you must in order:

- 1. edit the plugin configuration file
- 2. login as admin and go to the plugin management interface
- 3. click on the **Update Plugins** button

See Plugin Configuration for further details.

From:

https://wiki.i-mscp.net/ - i-MSCP Documentation

Permanent iink

https://wiki.i-mscp.net/doku.php?id=plugins:management&rev=1393217046

Last update: 2014/02/24 04:44

https://wiki.i-mscp.net/ Printed on 2024/04/01 06:39

×